

Package ‘SigBridgeR’

October 31, 2025

Title Multi-algorithm Integration of Phenotypic, scRNA-seq, and Bulk Data for Cell Screening

Version 2.5.3

Description SigBridgeR is an integrative toolkit designed to identify phenotype-associated cell sub-populations by combining phenotype(e.g. survival, drug sensitivity), bulk expression and single-cell RNA-seq data. It leverages multiple algorithms (including 'Scissor', 'sc-PAS', 'scPP', 'scAB' and 'DEGAS') to robustly link cell features with clinical or functional phenotypes. The package provides a unified pipeline for cross-modal data analysis, enabling the discovery of biologically and clinically relevant cell states in heterogeneous samples.

License GPL (>= 3)

Encoding UTF-8

URL <https://github.com/WangLabCSU/SigBridgeR>

BugReports <https://github.com/WangLabCSU/SigBridgeR/issues>

Roxygen list(markdown = TRUE)

RoxygenNote 7.3.3

Imports AUCell,
chk,
cli,
data.table,
DEGAS (>= 1.0.0),
dplyr,
edgeR,
fgsea,
ggforce,
ggplot2,
ggupset,
glue,
IDConverter (>= 0.3.5),
Matrix,
methods,
patchwork,
processx,
purrr,
reticulate,

rlang,
 scAB ($\geq 1.0.0$),
 Scissor ($\geq 2.0.0$),
 scPAS ($\geq 0.2.0$),
 ScPP ($\geq 0.0.0.9000$),
 Seurat ($\geq 5.0.0$),
 SeuratObject ($\geq 5.0.0$),
 tibble,
 tidyr

Depends R ($\geq 4.1.0$)

Remotes tsteeljohnson91/DEGAS,
 ShixiangWang/IDConverter,
 Qinran-Zhang/scAB,
 sunduanchen/Scissor,
 aiminXie/scPAS,
 WangX-Lab/ScPP

Suggests anndata,
 ggVennDiagram,
 here,
 knitr,
 matrixStats,
 org.Hs.eg.db,
 preprocessCore,
 randomcoloR,
 rmarkdown,
 zeallot

VignetteBuilder knitr

Contents

AddMisc	3
BulkPreProcess	4
DoDEGAS	6
DoscAB	10
DoScissor	12
DoscPAS	14
DoscPP	16
FindRobustElbow	18
ListPyEnv	19
LoadRefData	21
MergeResult	22
SCPreProcess	23
Screen	28
ScreenFractionPlot	31
ScreenUpset	33
SetupPyEnv	35

AddMisc 3

SetupPyEnv.conda 36
SetupPyEnv.venv 38
SymbolConvert 40

Index 41

AddMisc *Safely Add Miscellaneous Data to Seurat Object*

Description

Adds arbitrary data to the @misc slot of a Seurat object with automatic key conflict resolution. If the key already exists, automatically appends a numeric suffix to ensure unique key naming (e.g., "mykey_1", "mykey_2").

Usage

```
AddMisc(  
  seurat_obj,  
  ..., # key = value  
  cover = TRUE # overwrite existing data  
)
```

Arguments

seurat_obj	A Seurat object to modify
...	key-value pairs to add to the @misc slot.
cover	Logical indicating whether to overwrite existing data. If (default TRUE).

Value

The modified Seurat object with added @misc data. The original object structure is preserved with no other modifications.

Key Generation Rules

1. If key doesn't exist: uses as-is
2. If key exists: appends the next available number (e.g., "key_1", "key_2")
3. If numbered keys exist (e.g., "key_2"): increments the highest number

Examples

```
## Not run:  
# Basic usage  
seurat_obj <- AddMisc(seurat_obj, "QC_stats" = qc_df)  
  
# Auto-incrementing example  
seurat_obj <- AddMisc(seurat_obj, markers = markers1)
```

```

seurat_obj <- AddMisc(seurat_obj, markers = markers2, cover=FALSE)
# Stores as "markers" and "markers_1"

## End(Not run)

```

BulkPreProcess

Bulk RNA-seq Data Preprocessing and Quality Control Function

Description

This function performs comprehensive preprocessing and quality control analysis for bulk RNA-seq data, including data validation, filtering, batch effect detection, principal component analysis, and visualization.

Usage

```

BulkPreProcess(
  data,
  sample_info = NULL,
  gene_symbol_conversion = FALSE,
  check = TRUE,
  min_count_threshold = 10,
  min_gene_expressed = 3,
  min_total_reads = 1e+06,
  min_genes_detected = 10000,
  min_correlation = 0.8,
  n_top_genes = 500,
  show_plot_results = TRUE,
  verbose = TRUE
)

```

Arguments

<code>data</code>	Expression matrix with genes as rows and samples as columns, or a list containing <code>count_matrix</code> and <code>sample_info</code>
<code>sample_info</code>	Sample information data frame (optional), ignored if <code>data</code> is a list. A qualified <code>sample_info</code> should contain both <code>sample</code> and <code>condition</code> columns (case-sensitive), and there are no specific requirements for the data type stored in the <code>condition</code> column.
<code>gene_symbol_conversion</code>	Whether to convert Ensembl version IDs and TCGA version IDs to genes with <code>IDConverter</code> , default: <code>FALSE</code>
<code>check</code>	Whether to perform detailed quality checks, default: <code>TRUE</code>
<code>min_count_threshold</code>	Minimum count threshold for gene filtering, default: 10

min_gene_expressed	Minimum number of samples a gene must be expressed in, default: 3
min_total_reads	Minimum total reads per sample, default: 1e6
min_genes_detected	Minimum number of genes detected per sample, default: 10000
min_correlation	Minimum correlation threshold between samples, default: 0.8
n_top_genes	Number of top variable genes for PCA analysis, default: 500
show_plot_results	Whether to generate visualization plots, default: TRUE
verbose	Whether to output detailed information, default: TRUE

Details

The function performs the following operations:

1. Data validation and format conversion
2. Basic statistics calculation (missing values, read depth, gene detection)
3. Optional detailed quality checks including:
 - Sample correlation analysis
 - Principal Component Analysis (PCA)
 - Outlier detection using Mahalanobis distance
 - Batch effect detection using ANOVA
4. Data filtering based on count thresholds and quality metrics
5. Optional gene symbol conversion
6. Visualization generation (PCA plots)

Value

Filtered count matrix

Quality Metrics

The function calculates and reports several quality metrics:

Data Integrity Number of missing values

Gene Count Total number of genes after filtering

Sample Read Depth Total reads per sample

Gene Detection Rate Number of genes detected per sample

Sample Correlation Pearson correlation between samples

PCA Variance Variance explained by first two principal components

Batch Effects Proportion of genes significantly affected by batch

Sample Information Format

The sample_info data frame should contain:

- sample** Character vector of unique sample identifiers
- condition** Character vector of experimental conditions
- batch** Optional character vector of batch identifiers

Filtering Criteria

Genes are retained if:

- They have counts \geq min_count_threshold in \geq min_gene_expressed samples

Samples are retained if:

- Total reads \geq min_total_reads
- Detected genes \geq min_genes_detected
- Mean correlation \geq min_correlation (if check=TRUE)

See Also

[cpm](#) for counts per million calculation, [prcomp](#) for PCA analysis, [cor](#) for correlation analysis, [SymbolConvert](#) for gene symbol conversion

DoDEGAS

Run DEGAS Analysis for Single-Cell and Bulk RNA-seq Data Integration

Description

This function performs DEGAS to integrate single-cell and bulk RNA-seq data, identifying phenotype-associated cells using a bootstrap aggregated multi-task learning approach.

Usage

```
DoDEGAS(
  select_fraction = 0.05,
  min_thresh = 0.4,
  matched_bulk,
  sc_data,
  phenotype = NULL,
  sc_data.pheno_colname = NULL,
  label_type = "DEGAS",
  phenotype_class = c("binary", "continuous", "survival"),
  tmp_dir = "tmp",
  env_params = list(),
  degas_params = list(),
```

```

normality_test_method = c("jarque-bera", "d'agostino", "kolmogorov-smirnov"),
verbose = TRUE,
...
)

```

Arguments

<code>select_fraction</code>	The top percentage of selected cells will be considered as Positive cells, without considering how much larger the possible correlation coefficient of the observation group is compared to that of the control group. Only used when <code>phenotype_class</code> is "binary" or "survival". (default: 0.05)
<code>min_thresh</code>	DEGAS will calculate the possible correlation coefficients for each cell related to the phenotype. When the coefficient of the observation group is at least <code>min_thresh</code> larger than that of the control group, it can be considered related to the phenotype and will be marked as Positive. The priority of <code>min_thresh</code> is higher than that of <code>select_fraction</code> . (default: 0.4)
<code>matched_bulk</code>	Bulk RNA-seq data as matrix or data.frame (rows=genes, columns=samples)
<code>sc_data</code>	Single-cell data as Seurat object containing RNA assay
<code>phenotype</code>	Bulk-level phenotype data. For classification: binary matrix with one-hot encoding. For survival: matrix with two columns (time and event status). Can be NULL, matrix, data.frame, or vector.
<code>sc_data.pheno_colname</code>	Column name for single-cell phenotype in metadata (if available)
<code>label_type</code>	Label type for DEGAS results (default: "DEGAS")
<code>phenotype_class</code>	Type of phenotype: "binary" (classification), "continuous", or "survival"
<code>tmp_dir</code>	Temporary directory for intermediate files (default: "tmp")
<code>env_params</code>	List of environment parameters for Python setup including: <ul style="list-style-type: none"> • <code>env.name</code>: environment name (default: "r-reticulate-degas") • <code>env.type</code>: environment type "conda", "environment", or "venv" (default: "environment") • <code>env.method</code>: environment setup method "system", "conda" (default: "system") • <code>env.file</code>: path to environment file (default: <code>system.file("conda/DEGAS_environment.yml", package = "SigBridgeR")</code>) • <code>env.python_version</code>: Python version (default: "3.9.15") • <code>env.packages</code>: named vector of Python packages and versions (default: <code>c("tensorflow" = "2.4.1", "protobuf" = "3.20", "numpy" = "any")</code>) • <code>env.recreate</code>: whether to recreate environment (default: FALSE) • <code>env.use_conda_forge</code>: whether to use conda-forge channel (conda only, default: TRUE) • <code>env.verbose</code>: verbose output (default: FALSE)
<code>degas_params</code>	List of DEGAS algorithm parameters including:

- `DEGAS.model_type`: model type ("BlankClass", "ClassBlank", "ClassClass", "ClassCox", "BlankCox")
- `DEGAS.architecture`: "Standard" (feed forward) or "DenseNet" (dense net)
- `DEGAS.ff_depth`: number of layers in model (≥ 1 , default: 3)
- `DEGAS.pyloc`: path to Python executable (default: NULL, automatic detection)
- `DEGAS.bag_depth`: bootstrap aggregation depth (≥ 1 , default: 5)
- `DEGAS.train_steps`: training steps (default: 2000)
- `DEGAS.scbatch_sz`: single-cell batch size (default: 200)
- `DEGAS.patbatch_sz`: patient batch size (default: 50)
- `DEGAS.hidden_feats`: hidden features (default: 50)
- `DEGAS.do_prc`: dropout percentage (default: 0.5)
- `DEGAS.lambda1`: regularization parameter 1 (default: 3.0)
- `DEGAS.lambda2`: regularization parameter 2 (default: 3.0)
- `DEGAS.lambda3`: regularization parameter 3 (default: 3.0)
- `DEGAS.seed`: random seed (default: 2)

`normality_test_method`

Method for normality testing: "jarque-bera", "d'agostino", or "kolmogorov-smirnov"

`verbose`

Logical, whether to print messages.

`...`

for future compatibility

Details

The function performs the following steps:

1. Validates input data and parameters
2. Sets up Python environment with required dependencies
3. Trains bootstrap aggregated DEGAS model using `runCCMTLBag`
4. Generates cell-level predictions using `predClassBag`
5. Applies statistical testing to identify phenotype-associated cells
6. Labels cells as "Positive" or "Other" based on selection criteria

Model type is automatically determined:

- `BlankClass`: only bulk phenotype specified (`scLab = NULL`)
- `ClassBlank`: only single-cell phenotype specified (`patLab = NULL`)
- `ClassClass`: both single-cell and bulk phenotypes specified
- `ClassCox`: single-cell phenotype + bulk survival data
- `BlankCox`: only bulk survival data specified

Value

A list containing:

- `scRNA_data`: Seurat object with DEGAS labels added to metadata
- `model`: The model trained using the input data, and it can be used for cell classification prediction.
- `DEGAS_prediction`: Data table with DEGAS predictions containing:
 - Predicted label probabilities for each cell
 - Cell labels ("Positive"/"Other") based on selection criteria
 - Difference scores for binary phenotypes
 - Cell identifiers

References

Johnson TS, Yu CY, Huang Z, Xu S, Wang T, Dong C, et al. Diagnostic Evidence GAUGE of Single cells (DEGAS): a flexible deep transfer learning framework for prioritizing cells in relation to disease. *Genome Med.* 2022 Feb 1;14(1):11.

See Also

[Vec2sparse](#) for the structure transformation of phenotype [jb.test.modified](#) for modified Jarque-Bera test [mad.test](#) for outlier detection using Median Absolute Deviation [runCCMTLBag.optimized](#) for DEGAS model training [predClassBag.optimized](#) for DEGAS model prediction [LabelBinaryCells](#) for binary classification [LabelSurvivalCells](#) for survival classification [LabelContinuousCells](#) for continuous classification

Other screen_method: [DoScissor\(\)](#), [DoscAB\(\)](#), [DoscPAS\(\)](#), [DoscPP\(\)](#)

Other DEGAS: [LabelBinaryCells\(\)](#), [LabelContinuousCells\(\)](#), [LabelSurvivalCells\(\)](#), [Vec2sparse\(\)](#), [predClassBag.optimized\(\)](#), [readOutputFiles.optimized\(\)](#), [runCCMTL.optimized\(\)](#), [runCCMTLBag.optimized\(\)](#), [writeInputFiles.optimized\(\)](#)

Examples

```
## Not run:
# Binary classification example
result <- DoDEGAS(
  select_fraction = 0.05, # `select_fraction` only used in binary and survival phenotyping
  matched_bulk = bulk_matrix,
  sc_data = seurat_obj,
  phenotype = bulk_phenotype,
  phenotype_class = "binary"
)

# Survival analysis example
result <- DoDEGAS(
  select_fraction = 0.05, # `select_fraction` only used in binary and survival phenotyping
  matched_bulk = bulk_matrix,
  sc_data = seurat_obj,
  phenotype = survival_data,
```

```

    phenotype_class = "survival"
)

## End(Not run)

```

DoscAB

Perform scAB Screening Analysis

Description

Implements the scAB algorithm to identify phenotype-associated cell subpopulations in single-cell RNA-seq data by integrating matched bulk expression and phenotype information. Uses non-negative matrix factorization (NMF) with dual regularization for phenotype association and cell-cell similarity.

Usage

```

DoscAB(
  matched_bulk,
  sc_data,
  phenotype,
  label_type = "scAB",
  phenotype_class = c("binary", "survival"),
  alpha = 0.005,
  alpha_2 = 5e-05,
  maxiter = 2000,
  tred = 2,
  verbose = TRUE,
  ...
)

```

Arguments

<code>matched_bulk</code>	Normalized bulk expression matrix (genes \times samples) where: - Columns match phenotype row names - Genes match features in <code>sc_data</code>
<code>sc_data</code>	Seurat object containing preprocessed single-cell data:
<code>phenotype</code>	Data frame with clinical annotations where: - Rows correspond to <code>matched_bulk</code> columns - For survival: contains time and status columns
<code>label_type</code>	Character specifying phenotype label type (e.g., "SBS1", "time"), stored in <code>scRNA_data@misc</code>
<code>phenotype_class</code>	Analysis mode: - "binary": Case-control design (e.g., responder/non-responder) - "survival": Time-to-event analysis data.frame
<code>alpha</code>	Coefficient of phenotype regularization (default=0.005).
<code>alpha_2</code>	Coefficient of cell-cell similarity regularization (default=5e-05).

<code>maxiter</code>	NMF optimization iterations (default=2000).
<code>tred</code>	Z-score threshold (default=2).
<code>verbose</code>	Logical indicating whether to print progress messages. Default: TRUE.
<code>...</code>	For future update.

Value

A list containing:

scRNA_data Filtered Seurat object with selected cells

scAB_result scAB screening result

LICENSE

Licensed under the GNU General Public License version 3 (GPL-3.0). A copy of the license is available at <https://www.gnu.org/licenses/gpl-3.0.en.html>.

References

Zhang Q, Jin S, Zou X. scAB detects multiresolution cell states with clinical significance by integrating single-cell genomics and bulk sequencing data. *Nucleic Acids Research*. 2022 Nov 28;50(21):12112–30.

See Also

Other screen_method: `DoDEGAS()`, `DoScissor()`, `DoscPAS()`, `DoscPP()`

Other scAB: `NMF.optimized()`, `create_scAB.v5()`, `findSubset.optimized()`, `scAB.optimized()`, `select_K.optimized()`

Examples

```
## Not run:
# Binary phenotype example
result <- DoscAB(
  matched_bulk = bulk_matrix,
  sc_data = seurat_obj,
  phenotype = clinical_df,
  label_type = "disease_status",
  phenotype_class = "binary",
  alpha = 0.005,
  alpha_2 = 5e-05,
  maxiter = 2000,
  tred = 2
)

## End(Not run)
```

Description

Identifies phenotype-associated cell subpopulations in single-cell data using regularized regression on matched bulk expression profiles.

Usage

```
DoScissor(
  path2load_scissor_cache = NULL,
  path2save_scissor_inputs = "Scissor_inputs.RData",
  matched_bulk,
  sc_data,
  phenotype,
  label_type = "scissor",
  alpha = c(0.05, NULL),
  cutoff = 0.2,
  scissor_family = c("gaussian", "binomial", "cox"),
  reliability_test = FALSE,
  reliability_test.n = 10,
  reliability_test.nfold = 10,
  cell_evaluation = FALSE,
  cell_evaluation.benchmark_data = "path_to_file.RData",
  cell_evaluation.FDR = 0.05,
  cell_evaluation.bootstrap_n = 100,
  verbose = TRUE,
  ...
)
```

Arguments

path2load_scissor_cache	Path to precomputed Scissor inputs (RData file). If provided, skips recomputation (default: NULL).
path2save_scissor_inputs	Path to save intermediate files (default: "Scissor_inputs.RData").
matched_bulk	Normalized bulk expression matrix (features × samples). Column names must match phenotype identifiers.
sc_data	Seurat object containing single-cell RNA-seq data.
phenotype	Clinical outcome data. Can be: - Vector: named with sample IDs - Data frame: with row names matching bulk columns
label_type	Character specifying phenotype label type (e.g., "SBS1", "time"), stored in scRNA_data@misc

<code>alpha</code>	Parameter used to balance the effect of the l1 norm and the network-based penalties. It can be a number or a searching vector. If <code>alpha = NULL</code> , a default searching vector is used. The range of <code>alpha</code> is between 0 and 1. A larger <code>alpha</code> lays more emphasis on the l1 norm.
<code>cutoff</code>	(default: 0.2). When <code>alpha=NULL</code> , the <code>cutoff</code> is used to determine the optimal <code>alpha</code> . Higher values increase specificity.
<code>scissor_family</code>	Model family for outcome type: - "gaussian": Continuous outcomes - "binomial": Binary outcomes (default) - "cox": Survival outcomes
<code>reliability_test</code>	Logical to perform stability assessment when <code>scissor_alpha</code> is specified as a value between 0 and 1.(default: TRUE).
<code>reliability_test.n</code>	Number of CV folds for reliability test (default: 10).
<code>reliability_test.nfold</code>	Cross-validation folds for reliability test (default: 10).
<code>cell_evaluation</code>	Logical to perform cell evaluation (default: FALSE).
<code>cell_evaluation.benchmark_data</code>	Path to benchmark data (RData file).
<code>cell_evaluation.FDR</code>	FDR threshold for cell evaluation (default: 0.05).
<code>cell_evaluation.bootstrap_n</code>	Number of bootstrap iterations for cell evaluation (default: 100).
<code>verbose</code>	Logical to print progress messages (default: TRUE).
<code>...</code>	Additional arguments passed to <code>Scissor.v5.optimized</code> .

Value

A list containing:

scRNA_data A Seurat object with screened cells containing metadata:

scissor "Positive"/"Negative"/"Neutral" classification

label_type Outcome label used

scissor_result Raw Scissor results

reliability_result If `reliability_test=TRUE`, contains:

statistic A value between 0 and 1

p p-value of the test statistic

AUC_test_real 10 values of AUC for real data

AUC_test_back A list of AUC for background data

cell_evaluation If `cell_evaluation=TRUE`, contains:

evaluation_res A data.frame with some supporting information for each Scissor selected cell

LICENSE

Licensed under the GNU General Public License version 3 (GPL-3.0). A copy of the license is available at <https://www.gnu.org/licenses/gpl-3.0.en.html>.

References

Sun D, Guan X, Moran AE, Wu LY, Qian DZ, Schedin P, et al. Identifying phenotype-associated subpopulations by integrating bulk and single-cell sequencing data. *Nat Biotechnol.* 2022 Apr;40(4):527–38.

See Also

Other screen_method: [DoDEGAS\(\)](#), [DoscAB\(\)](#), [DoscPAS\(\)](#), [DoscPP\(\)](#)

Other scissor: [Scissor.v5.optimized\(\)](#)

Examples

```
## Not run:
# Binary outcome example
res <- DoScissor(
  matched_bulk = bulk_matrix,
  sc_data = seurat_obj,
  phenotype = a_named_vector,
  scissor_family = "binomial"
)

## End(Not run)
```

DoscPAS

Perform scPAS Screening Analysis

Description

This function performs scPAS screening analysis by integrating bulk and single-cell RNA-seq data. It includes data filtering steps and wraps the core `scPAS::scPAS` function.

Usage

```
DoscPAS(
  matched_bulk,
  sc_data,
  phenotype,
  label_type = "scPAS",
  assay = "RNA",
  imputation = FALSE,
  imputation_method = c("KNN", "ALRA"),
  nfeature = 3000L,
  alpha = c(0.01, NULL),
  cutoff = 0.2,
  network_class = c("SC", "bulk"),
  scPAS_family = c("cox", "gaussian", "binomial"),
  permutation_times = 2000L,
```

```

    FDR_threshold = 0.05,
    independent = TRUE,
    verbose = TRUE,
    ...
)

```

Arguments

<code>matched_bulk</code>	Bulk RNA-seq data (genes x samples)
<code>sc_data</code>	Single-cell RNA-seq data (Seurat object and preprocessed)
<code>phenotype</code>	Phenotype data frame with sample annotations
<code>label_type</code>	Character specifying phenotype label type (e.g., "SBS1", "time"), stored in <code>scRNA_data@misc</code> . (default: "scPAS")
<code>assay</code>	Assay to use from <code>sc_data</code> (default: 'RNA')
<code>imputation</code>	Logical, whether to perform imputation (default: FALSE)
<code>imputation_method</code>	Character. Name of alternative method for imputation. (options: "KNN", "ALRA")
<code>nfeature</code>	Number of features to select (default: 3000, indicating that the top 3000 highly variable genes are selected for model training)
<code>alpha</code>	Numeric. Significance threshold. Parameter used to balance the effect of the l1 norm and the network-based penalties. It can be a number or a searching vector. If <code>alpha = NULL</code> , a default searching vector is used. The range of <code>alpha</code> is in $[0, 1]$. A larger <code>alpha</code> lays more emphasis on the l1 norm. (default: 0.01)
<code>cutoff</code>	Numeric. Cutoff value for selecting the optimal <code>alpha</code> value when <code>alpha = NULL</code> . (default: 0.2)
<code>network_class</code>	Network class to use (default: 'SC', indicating gene-gene similarity networks derived from single-cell data. The other one is 'bulk'.)
<code>scPAS_family</code>	Model family for analysis (options: "cox", "gaussian", "binomial")
<code>permutation_times</code>	Number of permutations to perform (default: 2000)
<code>FDR_threshold</code>	Numeric. FDR value threshold for identifying phenotype-associated cells (default: 0.05)
<code>independent</code>	Logical. The background distribution of risk scores is constructed independently of each cell. (default: TRUE)
<code>verbose</code>	Logical. Whether to print progress messages (default: TRUE)
<code>...</code>	Additional arguments passed to DoscPAS functions

Value

A Seurat object from scPAS analysis

LICENSE

Licensed under the GNU General Public License version 3 (GPL-3.0). A copy of the license is available at <https://www.gnu.org/licenses/gpl-3.0.en.html>.

References

Xie A, Wang H, Zhao J, Wang Z, Xu J, Xu Y. scPAS: single-cell phenotype-associated subpopulation identifier. Briefings in Bioinformatics. 2024 Nov 22;26(1):bbae655.

See Also

Other screen_method: [DoDEGAS\(\)](#), [DoScissor\(\)](#), [DoscAB\(\)](#), [DoscPP\(\)](#)
Other scPAS: [scPAS.optimized\(\)](#)

DoscPP	<i>Perform scPP screening analysis</i>
--------	--

Description

This function performs scPP screening on single-cell data using matched bulk data and phenotype information. It supports binary, continuous, and survival phenotype types.

Usage

```
DoscPP(  
  matched_bulk,  
  sc_data,  
  phenotype,  
  label_type = "scPP",  
  phenotype_class = c("Binary", "Continuous", "Survival"),  
  ref_group = 0,  
  Log2FC_cutoff = 0.585,  
  estimate_cutoff = 0.2,  
  probs = c(0.2, NULL),  
  verbose = TRUE,  
  ...  
)
```

Arguments

matched_bulk	Bulk expression data (genes × samples) where: - Column names must match phenotype row names
sc_data	Seurat object containing preprocessed single-cell data: - Normalized counts in RNA assay
phenotype	Data frame or tibble or named vector with: - Rownames matching matched_bulk columns - For survival: must contain time and status columns
label_type	Character specifying phenotype label type (e.g., "SBS1"), stored in scRNA_data@misc
phenotype_class	Analysis type (case-sensitive): - "Binary": Case-control studies (e.g., tumor/normal) - "Continuous": Quantitative traits (e.g., drug response) - "Survival": Time-to-event data (requires time/status columns)

<code>ref_group</code>	Reference group or baseline for binary comparisons, e.g. "Normal" for Tumor/Normal studies and 0 for 0/1 case-control studies. (default: 0)
<code>Log2FC_cutoff</code>	Minimum log2 fold-change for binary markers (default: 0.585)
<code>estimate_cutoff</code>	Effect size threshold for continuous traits (default: 0.2)
<code>probs</code>	A numeric value indicating the quantile cutoff for cell classification. This parameter can also be a numeric vector, in which case an optimal threshold will be selected based on the AUC and enrichment score.(default: 0.2)
<code>verbose</code>	Logical indicating whether to print progress messages. Default: TRUE.
<code>...</code>	For future update.

Value

A list containing:

scRNA_data Seurat object with added metadata:

ScPP "Positive"/"Negative"/"Neutral" classification

gene_list List of genes used for screening

AUC A data.frame with area under the ROC curve:

scPP_AUCup AUC for positive

scPP_AUCdown AUC for negative

Algorithm Steps

1. Data Validation: Checks sample alignment between bulk and phenotype data
2. Marker Selection: Identifies phenotype-associated genes from bulk data
3. Single-cell Screening: Projects bulk markers onto single-cell data
4. Cell Classification: Categorizes cells based on phenotype association

Reference

WangX-Lab/ScPP [Internet]. [cited 2025 Aug 31]. Available from: <https://github.com/WangX-Lab/ScPP>

See Also

Other screen_method: [DoDEGAS\(\)](#), [DoScissor\(\)](#), [DoscAB\(\)](#), [DoscPAS\(\)](#)

Other scPP: [Check0VarRows\(\)](#), [ScPP.optimized\(\)](#)

Examples

```
## Not run:
# Binary phenotype analysis
res <- DoscPP(
  matched_bulk = bulk_data,
  sc_data = seurat_obj,
```

```

    phenotype = ms_data,
    label_type = "SBS1",
    phenotype_class = "Binary"
  )

  # Survival analysis
  surv_res <- DoscPP(
    sc_data = seurat_obj,
    matched_bulk = bulk_data,
    phenotype = surv_df,
    label_type = "OS_status",
    phenotype_class = "Survival"
  )

  ## End(Not run)

```

FindRobustElbow	<i>Automatically determine optimal PCA dimensions using multiple robust methods</i>
-----------------	---

Description

This function combines multiple statistical approaches to automatically determine the optimal number of principal components (PCs) for downstream single-cell analysis. It integrates variance-based heuristics, elbow detection algorithms, and provides comprehensive visualization for result validation.

Usage

```
FindRobustElbow(obj, verbose = TRUE, ndims = 50)
```

Arguments

obj	A Seurat object that has PCA computed (after RunPCA)
verbose	Logical, if TRUE outputs detailed method results and creates visualization plot. If FALSE returns only the final dimension.
ndims	Integer, maximum number of dimensions to consider (default: 50)

Value

Integer, the recommended number of PCA dimensions for downstream analysis

See Also

Other single_cell_preprocess: [ClusterAndReduce\(\)](#), [FilterTumorCell\(\)](#), [ProcessSeuratObject\(\)](#), [QCPatternFilter\(\)](#)

Examples

```
## Not run:
# After running PCA on Seurat object
pbmc <- RunPCA(pbmc, npcs = 50)
optimal_dims <- FindRobustElbow(pbmc, verbose = TRUE)
pbmc <- FindNeighbors(pbmc, dims = 1:optimal_dims)

## End(Not run)
```

ListPyEnv*List Available Python Environments*

Description

Discovers and lists available Python environments of various types on the system. This generic function provides a unified interface to find Conda environments and virtual environments (venv) through S3 method dispatch.

Default method that lists all Python environments by combining results from Conda and virtual environment discovery methods.

Discovers Conda environments using multiple detection strategies for maximum reliability. First attempts to use system Conda commands, then falls back to reticulate's built-in Conda interface if Conda command is unavailable or fails. Returns empty data frame if Conda is not available or no environments are found.

Discovers virtual environments by searching common venv locations including user directories (~/.virtualenvs, ~/.venvs) and project folders (./venv, ../venv). Supports custom search paths through the venv_locations parameter. Returns empty data frame if no virtual environments are found in the specified locations.

Usage

```
ListPyEnv(
  env_type = c("all", "conda", "venv", "virtualenv"),
  timeout = 30000,
  venv_locations = c("~/virtualenvs", "~/venvs", "./venv", "../venv"),
  verbose = TRUE,
  ...
)

## Default S3 method:
ListPyEnv(
  env_type = c("all", "conda", "venv", "virtualenv"),
  timeout = 30000,
  venv_locations = c("~/virtualenvs", "~/venvs", "./venv", "../venv"),
  verbose = TRUE,
  ...
)
```

```

)

## S3 method for class 'conda'
ListPyEnv(
  env_type = c("all", "conda", "venv", "virtualenv"),
  timeout = 30000,
  venv_locations = c("~/virtualenvs", "~/venvs", "./venv", "./.venv"),
  verbose = TRUE,
  ...
)

## S3 method for class 'venv'
ListPyEnv(
  env_type = c("all", "conda", "venv", "virtualenv"),
  timeout = 30000,
  venv_locations = c("~/virtualenvs", "~/venvs", "./venv", "./.venv"),
  verbose = TRUE,
  ...
)

```

Arguments

<code>env_type</code>	Character string specifying the type of environments to list. One of: "all", "conda", "venv". Defaults to "all".
<code>timeout</code>	The maximum timeout time when using system commands, only effective when <code>env_type=conda</code> .
<code>venv_locations</code>	Character vector of directory paths to search for virtual environments. Default includes standard locations and common project directories.
<code>verbose</code>	Logical indicating whether to print verbose output.
<code>...</code>	For future use.

Details

The function uses S3 method dispatch to handle different environment types:

- "all": Combines results from all environment types using `rbind()`
- "conda": Searches for Conda environments using multiple methods:
 - Primary: `reticulate::conda_list()` for reliable environment detection
 - Fallback: System `conda info --envs` command for broader compatibility
- "venv": Searches common virtual environment locations including user directories and project folders

Each method includes comprehensive error handling and will return empty results with informative warnings if no environments are found or if errors occur during discovery.

Value

A data frame with the following columns:

- name - Character vector of environment names
- python - Character vector of paths to Python executables
- type - Character vector indicating environment type ("conda" or "venv")

Returns an empty data frame with these columns if no environments are found.

Examples

```
## Not run:
# List all Python environments
ListPyEnv("all")

# List only Conda environments
ListPyEnv("conda")

# List only virtual environments with custom search paths
ListPyEnv("venv", venv_locations = c("~/my_envs", "./project_env"))

## End(Not run)
```

LoadRefData

Download & Load Reference Data

Description

This function checks if the data already exists in a local cache. If not, it downloads the file from the remote repository using multiple sources with fallback.

Usage

```
LoadRefData(
  data_type = c("survival", "binary", "continuous"),
  path = NULL,
  cache = TRUE,
  timeout = 60
)
```

Arguments

data_type	The type of data to download. Must be one of "survival", "binary", or "continuous".
path	Optional path to save the downloaded file, default: NULL, saving in package.
cache	Logical. If TRUE (default), saves the data for future sessions.
timeout	Integer. Connection timeout in seconds (default: 60).

Value

The requested datasets, stored in a list.

Examples

```
## Not run:
ref_data <- LoadRefData(data_type = c("survival"))

## End(Not run)
```

MergeResult

Merge Multiple Screening Analysis Results

Description

Combines results from multiple single-cell screening analyses (Scissor, scPAS, scPP, or scAB) by merging their metadata and miscellaneous information while preserving the original expression data. Performs an inner join on cell barcodes to ensure only cells present in all inputs are retained.

Usage

```
MergeResult(...)
```

Arguments

... Input objects to merge. Can be: - Seurat objects - Lists containing scRNA_data (Seurat objects) - Mixed combinations of the above - The first one will be used as base object for merging, priority given to first one when duplicate columns are found

Value

A merged Seurat object containing:

- Expression data from the first input object
- Combined metadata from all input objects
- Miscellaneous information from all input objects
- Only cells present in all input objects (inner join)

Processing Details

1. Input Validation: Checks for valid Seurat objects or lists containing Seurat objects
2. Metadata Extraction: Collects metadata from all objects
3. Cell Intersection: Retains only cells present in all datasets
4. Object Merging: Creates new Seurat object with combined metadata
5. Miscellaneous: Adds miscellaneous information to the merged object

Examples

```
## Not run:
# Merge mixed analysis types
combined <- MergeResult(scissor_output, scAB_output, scPP_output)

# Merge list-containing objects
merged_list <- MergeResult(list1, list2, seurat_obj)

## End(Not run)
```

SCPreProcess

Single-Cell RNA-seq Preprocessing Pipeline

Description

A generic function for standardized preprocessing of single-cell RNA-seq data from multiple sources. Handles data.frame/matrix, AnnData, and Seurat inputs with tumor cell filtering. Implements a complete analysis pipeline from raw data to clustered embeddings.

Usage

```
SCPreProcess(sc, ...)
```

```
SCPreProcess(sc, ...)
```

```
## Default S3 method:
```

```
SCPreProcess(
  sc,
  meta_data = NULL,
  column2only_tumor = NULL,
  project = "SC_Screening_Proj",
  min_cells = 400L,
  min_features = 0L,
  quality_control = TRUE,
  quality_control.pattern = c("^MT-"),
  data_filter = TRUE,
  data_filter.nFeature_RNA_thresh = c(200L, 6000L),
  data_filter.percent.mt = 20L,
  normalization_method = "LogNormalize",
  scale_factor = 10000L,
  scale_features = NULL,
  selection_method = "vst",
  resolution = 0.6,
  dims = NULL,
  verbose = TRUE,
  ...
)
```

```

)

## S3 method for class 'matrix'
SCPreProcess(
  sc,
  meta_data = NULL,
  column2only_tumor = NULL,
  project = "SC_Screening_Proj",
  min_cells = 400L,
  min_features = 0L,
  quality_control = TRUE,
  quality_control.pattern = c("^MT-", "^mt-"),
  data_filter = TRUE,
  data_filter.nFeature_RNA_thresh = c(200L, 6000L),
  data_filter.percent.mt = 20L,
  normalization_method = "LogNormalize",
  scale_factor = 10000L,
  scale_features = NULL,
  selection_method = "vst",
  resolution = 0.6,
  dims = NULL,
  verbose = TRUE,
  ...
)

## S3 method for class 'data.frame'
SCPreProcess(
  sc,
  meta_data = NULL,
  column2only_tumor = NULL,
  project = "SC_Screening_Proj",
  min_cells = 400L,
  min_features = 0L,
  quality_control = TRUE,
  quality_control.pattern = c("^MT-", "^mt-"),
  data_filter = TRUE,
  data_filter.nFeature_RNA_thresh = c(200L, 6000L),
  data_filter.percent.mt = 20L,
  normalization_method = "LogNormalize",
  scale_factor = 10000L,
  scale_features = NULL,
  selection_method = "vst",
  resolution = 0.6,
  dims = NULL,
  verbose = TRUE,
  ...
)

```



```

## S3 method for class 'dgCMatrx'
SCPreProcess(
  sc,
  meta_data = NULL,
  column2only_tumor = NULL,
  project = "SC_Screening_Proj",
  min_cells = 400L,
  min_features = 0L,
  quality_control = TRUE,
  quality_control.pattern = c("^MT-", "^mt-"),
  data_filter = TRUE,
  data_filter.nFeature_RNA_thresh = c(200L, 6000L),
  data_filter.percent.mt = 20L,
  normalization_method = "LogNormalize",
  scale_factor = 10000L,
  scale_features = NULL,
  selection_method = "vst",
  resolution = 0.6,
  dims = NULL,
  verbose = TRUE,
  ...
)

## S3 method for class 'AnnDataR6'
SCPreProcess(
  sc,
  meta_data = NULL,
  column2only_tumor = NULL,
  project = "SC_Screening_Proj",
  min_cells = 400L,
  min_features = 0L,
  quality_control = TRUE,
  quality_control.pattern = c("^MT-", "^mt-"),
  data_filter = TRUE,
  data_filter.nFeature_RNA_thresh = c(200L, 6000L),
  data_filter.percent.mt = 20L,
  normalization_method = "LogNormalize",
  scale_factor = 10000L,
  scale_features = NULL,
  selection_method = "vst",
  resolution = 0.6,
  dims = NULL,
  verbose = TRUE,
  ...
)

## S3 method for class 'Seurat'
SCPreProcess(sc, column2only_tumor = NULL, verbose = TRUE, ...)

```

Arguments

<code>sc</code>	Input data, one of: <ul style="list-style-type: none"> • <code>data.frame/matrix/dgCMatrix</code>: Raw count matrix (features x cells) • <code>AnnDataR6</code>: Python <code>AnnData</code> object via <code>reticulate</code> • <code>Seurat</code>: Preprocessed <code>Seurat</code> object
<code>...</code>	Additional arguments passed to specific methods. Currently unused.
<code>meta_data</code>	A <code>data.frame</code> containing metadata for each cell. It will be added to the <code>Seurat</code> object as <code>@meta.data</code> . If <code>NULL</code> , it will be extracted from the input object if possible.
<code>column2only_tumor</code>	A character of column names in <code>meta_data</code> , used to filter the <code>Seurat</code> object to only tumor cells. If <code>NULL</code> , no filtering is performed.
<code>project</code>	A character of project name, used to name the <code>Seurat</code> object.
<code>min_cells</code>	Minimum number of cells that must express a feature for it to be included in the analysis. Defaults to 400.
<code>min_features</code>	Minimum number of features that must be detected in a cell for it to be included in the analysis. Defaults to 0.
<code>quality_control</code>	Logical indicating whether to perform mitochondrial percentage quality control. Defaults to <code>TRUE</code> .
<code>quality_control.pattern</code>	Character pattern to identify mitochondrial genes, ribosomal protein genes, or other unwanted genes, as well as combinations of these genes. Customized patterns are supported. Defaults to <code>"^MT-"</code> .
<code>data_filter</code>	Logical indicating whether to filter cells based on quality metrics. Defaults to <code>TRUE</code> .
<code>data_filter.nFeature_RNA_thresh</code>	Numeric vector of length 2 specifying the minimum and maximum number of features per cell. Defaults to <code>c(200, 6000)</code> .
<code>data_filter.percent.mt</code>	Maximum mitochondrial percentage allowed. Defaults to 20.
<code>normalization_method</code>	Method for normalization: <code>"LogNormalize"</code> , <code>"CLR"</code> , or <code>"RC"</code> . Defaults to <code>"LogNormalize"</code> .
<code>scale_factor</code>	Scaling factor for normalization. Defaults to 10000.
<code>scale_features</code>	Features to use for scaling. If <code>NULL</code> , uses all variable features. Defaults to <code>NULL</code> .
<code>selection_method</code>	Method for variable feature selection: <code>"vst"</code> , <code>"mvp"</code> , or <code>"disp"</code> . Defaults to <code>"vst"</code> .
<code>resolution</code>	Resolution parameter for clustering. Higher values lead to more clusters. Defaults to 0.6.
<code>dims</code>	Dimensions to use for clustering and dimensionality reduction. If <code>NULL</code> , automatically determined by elbow method. Defaults to <code>NULL</code> .
<code>verbose</code>	Logical indicating whether to print progress messages. Defaults to <code>TRUE</code> .

Value

A Seurat object containing:

- Data filter and quality control
- Normalized and scaled expression data
- Variable features
- PCA/tSNE/UMAP reductions
- Cluster identities
- When tumor cells filtered: original dimensions in @misc\$raw_dim
- Final dimensions in @misc\$self_dim

See Also

[CreateSeuratObject](#), [NormalizeData](#), [ScaleData](#), [FindVariableFeatures](#), [RunPCA](#), [RunTSNE](#), [RunUMAP](#), [FindNeighbors](#), [FindClusters](#)

Examples

```
## Not run:
# Example with matrix input
counts_matrix <- matrix(rpois(1000, 5), nrow = 100, ncol = 10)
rownames(counts_matrix) <- paste0("Gene", 1:100)
colnames(counts_matrix) <- paste0("Cell", 1:10)

seurat_obj <- SCPreProcess(
  sc = counts_matrix,
  project = "TestProject",
  min_features = 50,
  resolution = 0.8
)

# Example with tumor cell filtering
metadata <- data.frame(
  cell_type = c(rep("Tumor", 5), rep("Normal", 5)),
  row.names = paste0("Cell", 1:10)
)

tumor_seurat <- SCPreProcess(
  sc = counts_matrix,
  meta_data = metadata,
  column2only_tumor = "cell_type",
  project = "TumorAnalysis"
)

## End(Not run)
```

Screen

*Single-Cell Data Screening***Description**

Integrates matched bulk expression data and phenotype information to identify phenotype-associated cell populations in single-cell RNA-seq data using one of four computational methods. Ensures consistency between bulk and phenotype data before analysis.

Usage

```
Screen(
  matched_bulk,
  sc_data,
  phenotype,
  label_type = NULL,
  phenotype_class = c("binary", "survival", "continuous"),
  screen_method = c("Scissor", "scPP", "scPAS", "scAB", "DEGAS"),
  ...
)
```

Arguments

<code>matched_bulk</code>	Matrix or data frame of preprocessed bulk RNA-seq expression data (genes x samples). Column names must match names/IDs in phenotype.
<code>sc_data</code>	A Seurat object containing scRNA-seq data to be screened.
<code>phenotype</code>	Phenotype data, either: - Named vector (names match <code>matched_bulk</code> columns), or - Data frame with row names matching <code>matched_bulk</code> columns
<code>label_type</code>	Character specifying phenotype label type (e.g., "SBS1", "time")
<code>phenotype_class</code>	Type of phenotypic outcome (must be consistent with input data): - "binary": Binary traits (e.g., case/control) - "continuous": Continuous measurements - "survival": Survival objects
<code>screen_method</code>	Screening algorithm to use, there are four options: - "Scissor": see also <code>DoScissor()</code> - "scPP": see also <code>DoscPP()</code> - "scPAS": see also <code>DoscPAS()</code> - "scAB": see also <code>DoscAB()</code> , no continuous support - "DEGAS": see also <code>DoDEGAS()</code>
<code>...</code>	Additional method-specific parameters:
	Scissor alpha (numeric or NULL) Significance threshold. When NULL, alpha will keep increasing iteratively until the corresponding cells are screened out, default 0.05
	cutoff (numeric) A threshold for terminating the iteration of alpha, only work when alpha is NULL, default 0.2
	path2load_scissor_cache (character) default NULL

path2save_scissor_inputs (character) A path to save the intermediary data. By using `path2load_scissor_cache`, the intermediary data can be loaded from the specified path. default "Scissor_inputs.RData"

reliability_test (logical) Whether to perform reliability test, default FALSE

reliability_test.nfold (integer) Cross-validation folds for reliability test, default 10

reliability_test.n (integer) Number of cells to use for reliability test, default 10

cell_evaluation (logical) Whether to perform cell evaluation, default FALSE

cell_evaluation.benchmark_data .RData Benchmark data for cell evaluation, default NULL

cell_evaluation.FDR (numeric) FDR threshold for cell evaluation, default 0.05

cell_evaluation.bootstrap_n (integer) Number of bootstrap samples for cell evaluation, default 10

scPP ref_group (integer or character) Reference group or baseline for **binary** comparisons, e.g. "Normal" for Tumor/Normal studies and 0 for 0/1 case-control studies. default: 0

Log2FC_cutoff (numeric) Minimum log2 fold-change for binary markers, default 0.585

estimate_cutoff (numeric) Effect size threshold for **continuous** traits, default 0.2

probs (numeric) Quantile cutoff for cell classification, default 0.2

scPAS assay (character) Assay to use from `sc_data`, default "RNA"

imputation (logical) Whether to perform imputation, default FALSE

nfeature (integer) Number of features to select, default 3000

alpha (numeric or NULL) Significance threshold, When NULL, alpha will keep increasing iteratively until the corresponding cells are screened out, default 0.01

independent (logical) The background distribution of risk scores is constructed independently of each cell. default: TRUE

network_class (character) Network class to use. default: 'SC', indicating gene-gene similarity networks derived from single-cell data. The other one is 'bulk'.

permutation_times (integer) Number of permutations, default 2000

FDR_threshold (numeric) FDR value threshold for identifying phenotype-associated cells default 0.05

scAB alpha (numeric) Coefficient of phenotype regularization ,default 0.005

alpha_2 (numeric) Coefficient of cell-cell similarity regularization, default 5e-05

maxiter (integer) NMF optimization iterations, default 2000

tred (integer) Z-score threshold, default 2

DEGAS sc_data.pheno_colname (character) Phenotype column name in `sc_data`, default "NULL"

select_fraction (numeric) Fraction of cells to select for DEGAS, default 0.05
tmp_dir (character) Temporary directory for DEGAS, default "NULL"
env_params (list) Environment parameters for DEGAS, default "list()"
degas_params (list) DEGAS parameters, default "list()"
normality_test_method (character) Normality test method for DEGAS, default "jarque-bera"

Value

A list containing:

scRNA_data Filtered Seurat object with phenotype-associated cells

Some screen_result Important information about the screened result related to the selected method

Data Matching Requirements

- matched_bulk column names and phenotype names/rownames must be identical
- Phenotype values must correspond to bulk samples (not directly to single cells)
- Mismatches will trigger an error before analysis begins, and there is a built-in pre-run check.

Method Compatibility

Method	Supported Phenotypes	Additional Parameters
Scissor	All three types	alpha, cutoff, path2load_scissor_cache, path2save_scissor_inputs, reliabil
scPP	All three types	ref_group, Log2FC_cutoff, estimate_cutoff, probs
scPAS	All three types	n_components ,assay, imputation,nfeature, alpha,network_class,permutation_t
scAB	Binary/Survival	alpha, alpha_2, maxiter, tred
DEGAS	All three types	sc_data.pheno_colname,select_fraction,tmp_dir,env_params,degas_params,nor

See Also

- Associated functions:
- [DoScissor](#)
 - [DoscPP](#)
 - [DoscPAS](#)
 - [DoscAB](#)
 - [DoDEGAS](#)

ScreenFractionPlot *Visualization of Cell Screening Fractions*

Description

Generates stacked bar plots showing the proportion of cells classified as Positive/Negative/Neutral by single-cell screening algorithms (Scissor, scPAS, scPP, or scAB) across different sample groups. Supports both single and multiple screen types visualization.

Usage

```
ScreenFractionPlot(
  screened_seurat,
  group_by = "Source", # x-axis label
  screen_type = NULL, # default: search all available screens
  show_null = FALSE,
  plot_color = NULL, # stack bar color of each status
  show_plot = FALSE,
  plot_title = "Screen Fraction",
  stack_width = 0.85,
  x_text_angle = 45,
  axis_linewidth = 0.8,
  legend_position = "right",
  x_lab = NULL,
  y_lab = "Fraction of Status",
  ncol = 2, # number of columns for facet wrap
  nrow = NULL, # number of rows for facet wrap
  ... # unused
)
```

Arguments

screened_seurat	A Seurat object containing screening results in metadata. Must contain columns corresponding to screen_type.
group_by	Metadata column name for grouping samples (default: "Source").
screen_type	Screening algorithm(s) used. Can be a single value or vector. Must match meta-data column(s) (case-sensitive, e.g., "scissor" for Scissor results).
show_null	Logical whether to show groups with zero cells (default: FALSE).
plot_color	Custom color palette (named vector format): - Required names: "Positive", "Negative", "Neutral" - Default: c("Neutral"="#CECECE", "Other"="#CECECE", "Positive"="#ff3333", "Negative"="#386c9b")
show_plot	Logical to immediately display plot (default: TRUE).
plot_title	Plot title (default: "Screen Fraction"). When multiple screen types, can be a vector of titles or single title (will append screen type).

<code>stack_width</code>	Bar width (default: 0.85).
<code>x_text_angle</code>	X-axis label angle (default: 45).
<code>axis_linewidth</code>	Axis line thickness (default: 0.8).
<code>legend_position</code>	Legend position (default: "right").
<code>x_lab</code>	X-axis label (default: NULL).
<code>y_lab</code>	Y-axis label (default: "Fraction of Status").
<code>ncol</code>	Number of columns for facet wrap when multiple screen types (default: 2).
<code>nrow</code>	Number of rows for facet wrap when multiple screen types (default: NULL).
<code>...</code>	Other arguments passed to <code>ggplot2::theme()</code>

Value

A list containing:

- `stats`: A data frame (single screen) or list of data frames (multiple screens) with screening statistics including:
 - Grouping variable counts
 - Raw cell counts
 - Percentage fractions
- `plot`: A `ggplot2` object (single screen) or list of `ggplot2` objects (multiple screens)
- `combined_plot`: A combined plot using `patchwork` (only for multiple screens)

Visualization Details

- Bars are ordered by descending Positive fraction
- Y-axis shows percentage (0-100%)
- Zero-fraction groups are automatically hidden unless `show_null=TRUE`
- For multiple screen types, plots can be combined using `patchwork`

See Also

Other visualization_function: [ScreenUpset\(\)](#)

Examples

```
## Not run:
# Single screen type usage
res <- ScreenFractionPlot(
  screened_seurat = scissor_result,
  group_by = "PatientID",
  screen_type = "scissor"
)

# Multiple screen types at once
multi_res <- ScreenFractionPlot(
```



```

screened_seurat = multi_screened_result,
group_by = "TissueType",
screen_type = c("scissor", "scPAS", "scPP", "scAB", "DEGAS"),
ncol = 2
)

## End(Not run)

```

ScreenUpset

ScreenUpset - Visualize cell type intersections from screened Seurat object

Description

This function creates an UpSet plot to visualize intersections between different screening methods (e.g., scissor, scAB, scPAS, scPP) in a Seurat object metadata. It calculates all possible combinations of screening types and displays the number of cells positive for each combination.

Usage

```

ScreenUpset(
  screened_seurat,
  screen_type = NULL,
  show_plot = FALSE,
  n_intersections = 20,
  x_lab = "Screen Set Intersections",
  y_lab = "Number of Cells",
  title = "Cell Counts Across Screen Set Intersections",
  bar_color = "#4E79A7",
  combmatrix_point_color = "black",
  ...
)

```

Arguments

<code>screened_seurat</code>	A Seurat object containing screening results in metadata. Must contain columns with screening types marked as "Positive".
<code>screen_type</code>	Character vector of screening types to analyze. Default: NULL, indicating that a self-search pattern will be used.
<code>show_plot</code>	Whether to show the upset plot. Default: FALSE
<code>n_intersections</code>	Number of intersections to display in the plot. Default: 20.
<code>x_lab</code>	Label for the x-axis. Default: "Screen Set Intersections".
<code>y_lab</code>	Label for the y-axis. Default: "Number of Cells".

<code>title</code>	Plot title. Default: "Cell Counts Across Screen Set Intersections".
<code>bar_color</code>	Color for the bars in the plot. Default: "#4E79A7".
<code>combmatrix_point_color</code>	Color for points in the combination matrix. Default: "black".
<code>...</code>	Additional arguments passed to <code>ggplot2::theme()</code> for customizing the plot appearance.

Details

The function performs the following steps:

1. Validates input parameters and checks if specified screening types exist in metadata
2. Generates all possible combinations of screening types (from 1 to the total number of types)
3. Creates a logical matrix of positive cells for efficient computation
4. Calculates cell counts for each intersection using vectorized operations
5. Creates an UpSet plot visualization with customizable appearance

Value

A list containing two elements:

- `plot`: A `ggplot` object displaying the UpSet plot
- `stats`: A data frame with intersection statistics including:
 - `intersection`: Name of the intersection
 - `sets`: List of screening types in the intersection
 - `count`: Number of cells positive for all screening types in the intersection

See Also

Other visualization_function: [ScreenFractionPlot\(\)](#)

Examples

```
## Not run:
# Basic usage with default parameters
result <- ScreenUpset(screened_seurat = my_seurat_obj)

# Customize screening types and appearance
result <- ScreenUpset(
  screened_seurat = my_seurat_obj,
  screen_type = c("scissor", "scAB"),
  n_intersections = 15,
  title = "Custom Title",
  bar_color = "darkred"
)

## End(Not run)
```

Description

Sets up a Python environment with specified packages for DEGAS screening methods. This function can create new environments or reuse existing ones, supporting both Conda and venv environment types. It ensures all required dependencies are properly installed and verified.

Default method for unsupported environment types. Throws an informative error with supported environment types.

Usage

```
SetupPyEnv(env_type = c("conda", "venv"), ...)
```

```
## Default S3 method:
```

```
SetupPyEnv(env_type = c("conda", "venv"), ...)
```

Arguments

<code>env_type</code>	Character string specifying the type of Python environment to create or use. One of: "conda", "venv".
<code>...</code>	Additional parameters passed to specific environment methods.

Details

This function provides a comprehensive solution for Python environment management in R projects, particularly for machine learning workflows requiring TensorFlow. Key features include:

- **Environment Creation:** Automatically creates new environments or reuses existing ones with the same name
- **Package Management:** Installs specified Python packages with version pinning support
- **Verification:** Validates environment setup and package installations
- **Flexible Methods:** Supports different backend methods for environment creation (reticulate vs system calls)

The function uses S3 method dispatch to handle different environment types, allowing for extensible support of additional environment managers in the future.

Value

A data frame containing verification results for the environment setup, including installation status of all required packages. Invisibly returns the verification results.

See Also

[reticulate::conda_create\(\)](#), [reticulate::virtualenv_create\(\)](#) for underlying environment creation functions.

Examples

```
## Not run:
# Setup a Conda environment with default parameters
SetupPyEnv("conda")

# Setup a venv environment
SetupPyEnv("venv")

## End(Not run)
```

SetupPyEnv.conda

Setup Conda Python Environment

Description

Creates and configures a Conda environment specifically designed for screening workflows. This function provides multiple methods for environment creation and package installation, including support for environment files, with comprehensive verification and error handling.

Usage

```
## S3 method for class 'conda'
SetupPyEnv(
  env_type = "conda",
  env_name = "r-reticulate-degas",
  method = c("reticulate", "system", "environment"),
  env_file = NULL,
  python_version = "3.9.15",
  packages = c(tensorflow = "2.4.1", protobuf = "3.20.3"),
  recreate = FALSE,
  use_conda_forge = TRUE,
  verbose = TRUE,
  timeout = 1800000,
  ...
)
```

Arguments

env_type	Character string specifying the environment type. For this method, must be "conda".
env_name	Character string specifying the Conda environment name. Default: "r-reticulate-degas".
method	Character string specifying the method for environment creation and package installation. One of: "reticulate" (uses reticulate package), "system" (uses system conda commands), or "environment" (uses YAML environment file). Default: "reticulate".

<code>env_file</code>	Character string specifying the path to a Conda environment YAML file. Used when <code>method = "environment"</code> . Default: <code>NULL</code>
<code>python_version</code>	Character string specifying the Python version to install. Default: <code>"3.9.15"</code> .
<code>packages</code>	Named character vector of Python packages to install. Package names as names, versions as values. Use <code>"any"</code> for version to install latest available. Default includes <code>tensorflow</code> , <code>protobuf</code> , and <code>numpy</code> .
<code>recreate</code>	Logical indicating whether to force recreation of the environment if it already exists. Default: <code>FALSE</code> .
<code>use_conda_forge</code>	Logical indicating whether to use the conda-forge channel for package installation. Default: <code>TRUE</code> .
<code>verbose</code>	Logical indicating whether to display detailed progress messages and command output. Default: <code>TRUE</code> .
<code>timeout</code>	The maximum timeout time when using system commands, default: 30 minutes
<code>...</code>	For future compatibility.

Value

Invisibly returns `NULL`.

Note

The function requires Conda to be installed and accessible on the system `PATH` or through `reticulate`. For `method = "environment"`, the specified YAML file must exist and be properly formatted. The function includes extensive error handling but may fail if Conda is not properly configured.

See Also

`reticulate::conda_create()`, `reticulate::py_install()` for the underlying functions used in `reticulate` method.

Examples

```
## Not run:
# Setup using reticulate method (default)
SetupPyEnv.conda(
  env_name = "my-degas-env",
  python_version = "3.9.15"
)

# Setup using environment file
SetupPyEnv.conda(
  method = "environment",
  env_file = "path/to/environment.yml"
)

# Setup with custom packages
SetupPyEnv.conda(
  packages = c(
```

```

        "tensorflow" = "2.4.1",
        "scikit-learn" = "1.0.2",
        "pandas" = "any"
    )
)

## End(Not run)

```

SetupPyEnv.venv

Setup Virtual Environment (venv)

Description

Creates and configures a Python virtual environment (venv) specifically designed for screening workflows. This function provides a lightweight, isolated Python environment alternative to Conda environments with similar package management capabilities.

Usage

```

## S3 method for class 'venv'
SetupPyEnv(
  env_type = "venv",
  env_name = "r-reticulate-degas",
  python_version = "3.9.15",
  packages = c(tensorflow = "2.4.1", protobuf = "3.20.3"),
  python_path = NULL,
  recreate = FALSE,
  verbose = TRUE,
  ...
)

```

Arguments

env_type	Character string specifying the environment type. For this method, must be "venv".
env_name	Character string specifying the virtual environment name. Default: "r-reticulate-degas".
python_version	Character string specifying the Python version to use. Default: "3.9.15".
packages	Named character vector of Python packages to install. Package names as names, versions as values. Use "any" for version to install latest available. Default includes tensorflow, protobuf, and numpy.
python_path	Character string specifying the path to a specific Python executable. If NULL, uses the system default or installs the specified version. Default: NULL.
recreate	Logical indicating whether to force recreation of the virtual environment if it already exists. Default: FALSE.

verbose	Logical indicating whether to display detailed progress messages and command output. Default: TRUE.
...	For future compatibility.

Value

Invisibly returns NULL.

Note

Virtual environments require a base Python installation. If the specified Python version is not available, the function will attempt to install it using reticulate. Virtual environments are generally faster to create than Conda environments but may have more limited package availability compared to Conda-forge.

See Also

`reticulate::virtualenv_create()`, `reticulate::virtualenv_remove()`, `reticulate::use_virtualenv()` for the underlying virtual environment management functions.

Examples

```
## Not run:
# Setup virtual environment with default parameters
SetupPyEnv.venv()

# Setup with custom Python version and packages
SetupPyEnv.venv(
  env_name = "my-degas-venv",
  python_version = "3.8.12",
  packages = c(
    "tensorflow" = "2.4.1",
    "scikit-learn" = "1.0.2",
    "pandas" = "any"
  )
)

# Force recreate existing environment
SetupPyEnv.venv(
  env_name = "existing-env",
  recreate = TRUE
)

## End(Not run)
```

SymbolConvert	<i>Convert Ensembles Version IDs & TCGA Version IDs to Genes in Bulk Expression Data</i>
---------------	--

Description

Preprocess bulk expression data: convert Ensembles version IDs and TCGA version IDs to genes. NA values are replaced with unknown_k format (k stands for the position of the NA value in the row).

Usage

```
SymbolConvert(data)
```

Arguments

data	bulk expression data (matrix or data.frame)
------	---

Index

- * **DEGAS**
 - DoDEGAS, [6](#)
- * **scAB**
 - DoscAB, [10](#)
- * **scPAS**
 - DoscPAS, [14](#)
- * **scPP**
 - DoscPP, [16](#)
- * **scissor**
 - DoScissor, [12](#)
- * **screen_method**
 - DoDEGAS, [6](#)
 - DoscAB, [10](#)
 - DoScissor, [12](#)
 - DoscPAS, [14](#)
 - DoscPP, [16](#)
- * **single_cell_preprocess**
 - FindRobustElbow, [18](#)
- * **visualization_function**
 - ScreenFractionPlot, [31](#)
 - ScreenUpset, [33](#)
- AddMisc, [3](#)
- BulkPreProcess, [4](#)
- Check0VarRows, [17](#)
- ClusterAndReduce, [18](#)
- cor, [6](#)
- cpm, [6](#)
- create_scAB.v5, [11](#)
- CreateSeuratObject, [27](#)
- DoDEGAS, [6](#), [11](#), [14](#), [16](#), [17](#), [30](#)
- DoscAB, [9](#), [10](#), [14](#), [16](#), [17](#), [30](#)
- DoScissor, [9](#), [11](#), [12](#), [16](#), [17](#), [30](#)
- DoscPAS, [9](#), [11](#), [14](#), [14](#), [17](#), [30](#)
- DoscPP, [9](#), [11](#), [14](#), [16](#), [16](#), [30](#)
- FilterTumorCell, [18](#)
- FindClusters, [27](#)
- FindNeighbors, [27](#)
- FindRobustElbow, [18](#)
- findSubset.optimized, [11](#)
- FindVariableFeatures, [27](#)
- jb.test.modified, [9](#)
- LabelBinaryCells, [9](#)
- LabelContinuousCells, [9](#)
- LabelSurvivalCells, [9](#)
- ListPyEnv, [19](#)
- LoadRefData, [21](#)
- mad.test, [9](#)
- MergeResult, [22](#)
- NMF.optimized, [11](#)
- NormalizeData, [27](#)
- prcomp, [6](#)
- predClassBag.optimized, [9](#)
- ProcessSeuratObject, [18](#)
- QCPatternFilter, [18](#)
- readOutputFiles.optimized, [9](#)
- reticulate::conda_create(), [35](#), [37](#)
- reticulate::py_install(), [37](#)
- reticulate::use_virtualenv(), [39](#)
- reticulate::virtualenv_create(), [35](#), [39](#)
- reticulate::virtualenv_remove(), [39](#)
- runCCMTL.optimized, [9](#)
- runCCMTLBag.optimized, [9](#)
- RunPCA, [27](#)
- RunTSNE, [27](#)
- RunUMAP, [27](#)
- scAB.optimized, [11](#)
- ScaleData, [27](#)
- Scissor.v5.optimized, [14](#)
- scPAS.optimized, [16](#)

ScPP.optimized, [17](#)
SCPreProcess, [23](#)
Screen, [28](#)
ScreenFractionPlot, [31](#), [34](#)
ScreenUpset, [32](#), [33](#)
select_K.optimized, [11](#)
SetupPyEnv, [35](#)
SetupPyEnv.conda, [36](#)
SetupPyEnv.venv, [38](#)
SymbolConvert, [6](#), [40](#)

Vec2sparse, [9](#)

writeInputFiles.optimized, [9](#)